

TurfRx Fairway+

INCREASES ROOT DEVELOPMENT,
MICROBIAL DIVERSITY & RESPIRATION



GUARANTEED ANALYSIS

Total Nitrogen (N) 1%
 0.25%.....Ammoniacal Nitrogen
 0.25%.....Nitrate Nitrogen
 0.5%.....Urea Nitrogen
 Available Phosphate (P₂O₅) 7%
 Soluble Potash (K₂O) 12%
 ALSO CONTAINS NON-PLANT FOOD INGREDIENTS
 2% Humic Acid

WHY **TurfRx** Fairway+?

TurfRx Fairway+ is a phosphorus and potassium fertilizer, containing proprietary soluble carbon compounds. **TurfRx Fairway+** reduces abiotic stress, improves root development and increases soil microbial diversity due to humic, fulvic, and long-chain soluble carbon content. **TurfRx Fairway+** utilizes technology from its proprietary TurfRx formulations of **P+**, **K+**, and **C-85**.

PRODUCT USAGE

Turf Performance	Apply 0.5-3 gal/acre (1.5-9 oz./1000 ft ²) as a foliar/soil application every 1 to 6 weeks. Water in.
Grow-in	Apply 0.5-3 gal/acre (1.5-9 oz./1000 ft ²) as a soil application at seeding/sprigging. Repeat every 2 to 5 weeks. Water in.
Aerification	Apply 0.5-3 gal/acre (1.5-9 oz./1000 ft ²) as a soil application prior to aerification and repeat post-aerification. Water in.
Abiotic Stress Defense	Apply 0.5-3 gal/acre (1.5-9 oz./1000 ft ²) as a foliar/soil application every 1 to 6 weeks. Water in.
Heat Stress	Apply 0.5-3 gal/acre (1.5-9 oz./1000 ft ²) as a foliar/soil application every 1 to 6 weeks. Water in.
Thatch Reduction	Apply 0.5-3 gal/acre (1.5-9 oz./1000 ft ²) as a soil application every 1 to 6 weeks. Water in.
Root Development	Apply 0.5-3 gal/acre (1.5-9 oz./1000 ft ²) as a soil application every 1 to 6 weeks. Water in.

TurfRx
Fairway+ HANDLING GUIDELINES

PRE-MIXING

Pre-mixing is considered a best practice when sprayer agitation is not optimum. Proper hydration is essential for all applications. Recirculate or agitate while adding material.

ONCE THE MATERIAL IS ADDED TO WATER, CONSTANT AGITATION IS REQUIRED.

COMPATABILITY

Always jar test first.

Redox products are compatible with other Redox products when following product handling guidelines.

Use caution with reactive materials. For example, phosphorus and calcium.

Avoid extreme shifts in tank pH. When utilizing Redox materials that acidify, check tank pH prior to adding buffers.

TANK MIXING/INJECTION

Use of an anti-foaming agent is recommended. Fill the tank 50% full with water and initiate tank agitation prior to adding materials.

Don't add material too quickly—this allows for more thorough hydration.

The use of inductor assemblies is encouraged.

Recirculate or agitate while adding material.

ONCE THE MATERIAL IS ADDED TO WATER, CONSTANT AGITATION IS REQUIRED.

Rinse after use.

REFER TO PRODUCT HANDLING GUIDELINES FOR ADDITIONAL MIXING INSTRUCTIONS.
